

PART II

PREDICTING WIND EROSION LOSSES

SECTION C

THE FOLLOWING SECTION CONTAINS INFORMATION NEEDED TO CALCULATE WIND EROSION BY BOTH THE CRITICAL PERIOD METHOD AND THE MANAGEMENT PERIOD METHOD.

FIGURE 1

"C" CLIMATIC FACTORS

WYOMING




TABLE 1

PREVAILING WIND EROSION DIRECTION AND DEVIATION

PREVAILING WIND EROSION DIRECTION IN DEGREES	ANGLE OF DEVIATION FOR ROWS PLANTED	
	E-W	N-S
22.5	22.5	67.5
45.0	45.0	45.0
67.5	67.5	22.5
90.0	90.0	0.0
112.5	67.5	22.5
135.0	45.0	45.0
157.5	22.5	67.5
180.0	0.0	90.0
202.5	22.5	67.5
225.0	45.0	45.0
247.5	67.5	22.5
270.0	90.0	0.0
292.5	67.5	22.5
315.0	45.0	45.0
337.5	22.5	67.5
360.0	0.0	90.0

1/ The angle of deviation is the angle between the prevailing wind erosion direction and a line perpendicular to, (1) the long side of the field or strip, when determining unsheltered distance using a wind erosion direction factor or, (2) to row direction when determining effect of wind direction on the ridge roughness factor.

TABLE 2

Wind Erodibility Group (WEG)	Predominant Soil Texture Class of Surface Layer	Index "I" T/Ac/Yr 1/	Soil Ridge Roughness "K" Value Parameters	
			Expected 2/	Known 3/
1	Very fine sand, fine sand, sand, or coarse sand.	The "I" value is found in FOTG, Section II, Cropland Interpretations, on pages with header labeled Cropland Interpretations for Erosion Predictions	1.0	
2	Loamy very fine sand, loamy fine sand, loamy sand, loamy coarse sand, or spartic organic soil materials.		1.0	
3	Very fine sandy loam, fine sandy loam, sandy loam, or coarse sandy loam.		1.0	
4	Clay, silty clay, noncalcareous clay loam, or silty clay loam with more than 35 percent clay.		0.8	
4L	Calcareous loam and silt loam, or calcareous clay loam and silty clay loam.		0.8	
5	Noncalcareous loam and silt loam with less than 20 percent clay, or sandy clay loam, sandy clay, and hemic organic soil materials.		0.7	
6	Noncalcareous loam and silt loam with more than 20 percent clay, or noncalcareous clay loam with less than 35 percent clay.		0.7	
7	Silt, noncalcareous silty clay loam with less than 35 percent clay, and fibric organic soil material.		0.5	
8	Soils not susceptible to wind erosion due to coarse fragments or wetness, wind erosion not a problem.	--	---	

- 1/ The soil erodibility index is based on the relationship of dry soil aggregates greater than .84mm to potential soil erosion.
- 2/ Default "K" is usually expected on this soil at the wind erosion period. Select "K" from this column when actual field condition is not known or predictable.
- 3/ Select the "K" value from Table 7 on Pages C-8 to C-10 that corresponds to the angle of deviation, ridge height, and ridge spacing when actual field condition is known.

TABLE 3

KNOLL ERODIBILITY ADJUSTMENT FACTOR FOR "I"	
Slope Change in Prevailing Wind Erosion Direction	COLUMN A Knoll Adjustment to "I" 1/
3	1.3
4	1.6
5	1.9
6	2.3
8	3.0
10	3.6
10 - 15 *	2.0
15 - 20 *	1.4
20+ *	1.0

* Factors above 10 percent slope change based on NRCS judgement. No research data available.

1/ After the knoll adjustment has been made, use the nearest available value for "I" in Table 2.

TABLE 4
I ADJUSTMENT GUIDELINES FOR CRUSTS

WEG	I	Maximum Management Period Adjustment for Crust ¹	Minimum Crusted I	Available E Table
1	310	.7	217	220
	250	.7	175	180
	220	.7	154	160
	180	.7	126	134
	160	.7	112	134
2	134	.5	67	86
3	86	.4	34	38
4	86	.4	34	38
4L	86	.4	34	38
5	56	.3	17	21
6	48	.3	14	21
7	38	.3	11	12

¹ The management period adjustment to "I" has not been validated by research and is based on NRCS judgement.

TABLE 5
WIND ERODIBILITY GROUPS AND
SOIL ERODIBILITY INDEX IRRIGATION ADJUSTMENTS

EWE Texture Wetness Factor	Predominant Soil Texture Class of Surface Layer	Wind Erodibility Group (WEG)	Soil Erodibility Index (I) (T/Ac/Yr)	Soil Erodibility Index (I) for Irrig. Soils (T/Ac/Yr)
1	Very fine sand, fine sand, sand or coarse sand.	1	310 250 220 180 160	310 250 220 160 134
1	Loamy very fine sand, loamy fine sand, loamy sand, loamy coarse sand, or sapric organic soil materials.	2	134	104
1	Very fine sandy loam, fine sandy loam, sandy loam, or coarse sandy loam.	3	86	56
3	Clay, silty clay, noncalcareous clay loam, or silty clay loam with more than 35% clay.	4	86	56
2	Calcareous loam and silt loam, or calcar- eous clay loam and silty clay loam.	4L	86	56
2	Noncalcareous loam and silt loam with less than 20% clay, or sandy clay loam, sandy clay, and hemic organic soil materials.	5	56	38
2	Noncalcareous loam and silt loam with more than 20% clay, or noncalcareous clay loam with less than 35% clay.	6	48	21
2	Silt, noncalcareous silty clay loam with less than 35% clay and fibric organic soil material.	7	38	21

TABLE 6
K FACTOR RANDOM ROUGHNESS ADJUSTMENTS VALUES


FIELD OPERATIONS	RANDOM ROUGHNESS (INCHES)
Chisel, sweeps	1.20
Chisel, straight point	1.50
Chisel, twisted shovels	1.90
Cultivator, field	0.70
Cultivator, row	0.70
Cultivator, ridge till	0.70
Disk, 1-way	1.20
Disk, heavy plowing	1.90
Disk, tandem	0.80
Drill, double disk	0.40
Drill, deep furrow	0.50
Drill, no-till	0.40
Drill, no-till into sod	0.30
Fertilizer applicator, anhyd knife	0.60
Harrow, spike	0.40
Harrow, tine	0.40
Lister	0.80
Manure injector	1.50
Moldboard plow	1.90
Mulch treader	0.40
Planter, no-till	0.40
Planter, row	0.40
Rodweeder	0.40
Rotary hoe	0.40
Vee ripper	1.20

Parameter values of "core" cropland field operations from the RUSLE Handbook. These values may be used in WEQ for Random Roughness. However the use of the Random Roughness photos in the RUSLE handbook (photos available in the Appendix) may be preferable, especially where roughness is due to residual sod material such as the crowns of plants with its attached roots and soil.

FIGURE 2

K_{rr} FACTOR RANDOM ROUGHNESS ADJUSTMENT GRAPH

Graph to convert random roughness heights (standard deviation in inches) to WEQ K-subfactors for random roughness



Random roughness is defined as the standard deviation of roughness heights in inches.

—□— | = 134 —■— | = 104 —▲— | = 86 —■— | < or = 56

TABLE 7
RIDGE ROUGHNESS "K" FACTOR

Angle of Deviation 1/ = 0°

Ridge Spacing (Inches)	Ridge Height (Inches)											
	0	1	2	3	4	5	6	7	8	9	10	11
7	1.0	0.7	0.5	0.5	---	---	---	---	---	---	---	---
10	1.0	0.8	0.5	0.5	0.6	---	---	---	---	---	---	---
14	1.0	0.8	0.6	0.5	0.5	0.6	---	---	---	---	---	---
18	1.0	0.9	0.6	0.5	0.5	0.5	0.7	---	---	---	---	---
20	1.0	0.9	0.6	0.5	0.5	0.5	0.6	0.8	0.8	---	---	---
24	1.0	0.9	0.7	0.5	0.5	0.5	0.5	0.7	0.8	0.8	---	---
30	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.6	0.7	0.8	---	---
36	1.0	0.9	0.8	0.6	0.5	0.5	0.5	0.5	0.6	0.7	0.8	---
38	1.0	0.9	0.8	0.6	0.5	0.5	0.5	0.5	0.6	0.7	0.8	---
40	1.0	0.9	0.8	0.6	0.5	0.5	0.5	0.5	0.6	0.7	0.8	0.8

TABLE 7 (Cont.)

RIDGE ROUGHNESS "K" FACTOR

Angle of Deviation 1/ = 22.5°

Ridge Spacing (Inches)	Ridge Height (Inches)											
	0	1	2	3	4	5	6	7	8	9	10	11
7	1.0	.07	.05	.05	---	---	---	---	---	---	---	---
10	1.0	0.8	0.6	0.5	0.5	---	---	---	---	---	---	---
14	1.0	0.8	0.6	0.5	0.5	0.6	---	---	---	---	---	---
18	1.0	0.9	0.6	0.5	0.5	0.5	0.6	---	---	---	---	---
20	1.0	0.9	0.7	0.5	0.5	0.5	0.6	0.7	0.8	---	---	---
24	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.6	0.8	0.8	---	---
30	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.5	0.7	0.8	---	---
36	1.0	0.9	0.8	0.6	0.5	0.5	0.5	0.5	0.6	0.7	0.8	---
38	1.0	1.0	0.8	0.6	0.5	0.5	0.5	0.5	0.6	0.6	0.8	---
40	1.0	1.0	0.8	0.6	0.6	0.5	0.5	0.5	0.5	0.6	0.7	0.8

1/ The angle between the prevailing wind erosion direction and a line perpendicular to ridge direction.

TABLE 7 (Cont.)

RIDGE ROUGHNESS "K" FACTOR

Angle of Deviation 1/ = 45°

Ridge Spacing (Inches)	Ridge Height (Inches)											
	0	1	2	3	4	5	6	7	8	9	10	11
7	1.0	0.8	0.5	0.5	---	---	---	---	---	---	---	---
10	1.0	0.8	0.6	0.5	0.5	---	---	---	---	---	---	---
14	1.0	0.9	0.6	0.5	0.5	0.5	---	---	---	---	---	---
18	1.0	0.9	0.7	0.6	0.5	0.5	0.5	---	---	---	---	---
20	1.0	0.9	0.7	0.6	0.5	0.5	0.5	0.6	0.7	---	---	---
24	1.0	0.9	0.8	0.6	0.5	0.5	0.5	0.5	0.6	0.8	---	---
30	1.0	1.0	0.8	0.6	0.5	0.5	0.5	0.5	0.5	0.6	---	---
36	1.0	1.0	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.6	0.6	---
38	1.0	1.0	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.6	---
40	1.0	1.0	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	0.6	0.7

TABLE 7 (Cont.)

RIDGE ROUGHNESS "K" FACTOR

Angle of Deviation 1/ = 67.5°

Ridge Spacing (Inches)	Ridge Height (Inches)											
	0	1	2	3	4	5	6	7	8	9	10	11
7	1.0	0.9	0.6	0.5	---	---	---	---	---	---	---	---
10	1.0	0.9	0.7	0.6	0.5	---	---	---	---	---	---	---
14	1.0	0.9	0.8	0.6	0.6	0.5	---	---	---	---	---	---
18	1.0	1.0	0.8	0.7	0.6	0.5	0.5	---	---	---	---	---
20	1.0	1.0	0.8	0.7	0.6	0.5	0.5	0.5	0.5	---	---	---
24	1.0	1.0	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	---	---
30	1.0	1.0	0.9	0.8	0.6	0.6	0.5	0.5	0.5	0.5	---	---
36	1.0	1.0	0.9	0.8	0.7	0.6	0.5	0.5	0.5	0.5	0.5	---
38	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	---
40	1.0	1.0	0.9	0.8	0.7	0.6	0.6	0.5	0.5	0.5	0.5	0.5

1/ The angle between the prevailing wind erosion direction and a line perpendicular to ridge direction.

TABLE 7 (Cont.)

RIDGE ROUGHNESS "K" FACTOR

Angle of Deviation $1/ = 90^\circ$

Ridge Spacing (Inches)	0	1	2	3	4	Ridge Height (Inches)	5	6	7	8	9	10	11
Soil ridge roughness, "K" Factor, is always 1.0 when prevailing wind direction is parallel to ridge pattern (angle of deviation = 90°).													

TABLE 8
ESTIMATING RESIDUE

Crop	Estimated Air Dry Residue Produced
Alfalfa	3,000 lbs./a.
Barley.....	80 lbs./bu.
Buckwheat.....	1.5 lbs./lb.
Corn	60 - 90 lbs./bu.
1/ Corn and/or Sorghum Silage.....	50 lbs. residue per inch of stubble height per 10,000 plants/a.
Dry Edible Beans.....	1.0 lbs./lb.
Field Peas	1.0 lbs./lb.
Flax	80 lbs./bu.
1/ Grain Sorghum.....	60 lbs./bu.
Lentils	1.0 lbs./lb.
Millet.....	80 lbs./bu.
Mustard.....	1.5 lbs./lb.
Oats.....	50 lbs./bu.
Rape Seed	1.5 lbs./lb.
Rye	120 lbs./bu.
Safflower.....	1.5 lbs./lb.
2/ Soybeans	50 lbs./bu.
Spring Wheat, Durum	100 lbs./bu.
Sugarbeets.....	150 lbs./ton
1/ Sunflower	2.2 lbs./lb.
Winter Wheat	120 lbs./bu.
3/ Potatoes, WEGs 1 & 2	
Irrigated, without desiccant	1,100 lbs. (575 lbs. SGe)
Irrigated, with desiccant	600 lbs. (250 lbs. SGe)
Dryland	0 lbs. (0 lbs. SGe)
3/ Potatoes, WEGs 3, 4, 5, 6, 7, & 8	
Irrigated, without desiccants	1,500 lbs. (850 lbs. SGe)
Irrigated, with desiccant	800 lbs. (375 lbs. SGe)
Dryland, without desiccant.....	1,000 lbs. (500 lbs. SGe)
Dryland, with desiccant	545 lbs. (240 lbs. SGe)

1/ Field experience in the Northern Great Plains indicates the ratio of residue to grain is higher when crops are grown in narrow row seedings. Research data is not available at this time to confirm this common observation. Until research is available, these residue production values may be increased 30 percent when these crops are planted in rows less than 20 inches apart.

- 2/ Soybeans are considered "narrow row" when planted in rows not over 14 inches apart. The most common spacing is 7 to 8 inches. Field experience in the Northern Great Plains indicates the ratio of residue to grain is higher when soybeans are grown in narrow row seedings, as compared to wide row seedings. Research data is not available, at this time, to confirm this common observation. Until research is available, a ratio of 65 pounds residue per bushel of grain may be used for narrow row soybeans.
- 3/ Potato residue varies significantly with potato varieties, time of harvest, fertility program, and leaf diseases. If the figures in this table are not accepted, the alternative of collecting surface residue and weighing is available. Refer to the Range Handbook for residue collecting or contact your state agronomist. A minimum of five collections will be required. Weights will be on an air dry basis.

The following information on residue reduction was developed from available research data, NRCS Field Office Technical Guides and from farm equipment manufacturers. Each tillage or planting operation reduces the residue that was present prior to the operation.

Crop residues have been generally classified as being either Nonfragile or Fragile as defined in Table 9, Residue Types. This is a subjective classification based on the ease in which crop residues are decomposed by the elements or buried by tillage operations. Plant characteristics such as composition and size of leaves and stems, density of the residue, and relative quantities produced were considered.

Many factors affect the amount of residue remaining after a pass with a tractor and tillage or planting implement. Residue amounts are sensitive to depth and speed of equipment operation and row spacing. When selecting values from the ranges in Table 10, Residue Reduction, for a specific implement, consider the following general rule of thumb.

- (1) At shallower operating depths, greater amounts of residue remain on the soil surface, while at deeper operating depths, more residue is buried.
- (2) Slower operating speeds tend to leave more residues on the soil surface while at faster speeds, more residue is buried. Under some conditions field cultivators, finishing tools with field cultivator gangs, some planters and drills may return as much as 20 percent of the residue incorporated at shallow depths by recent operations.
- (3) Excess wheel slippage, caused by improper ballasting of tractor tires, can destroy valuable residues in the wheel tracks.

Use the residue reduction figures in Table 10, Residue Reduction, as a guide in selecting the types of equipment and blades, points or sweeps used in the tillage system.

TABLE 9

RESIDUE TYPES

<u>NONFRAGILE</u>		<u>FRAGILE</u>
Alfalfa or legume hay	Triticale	Canola/Rapeseed Vegetables
Barley	Wheat	Dry Beans
Buckwheat	Sorghum	Dry Peas
Corn	Speltz	Fall seeded cover crops
Flax Seed		Green Peas
Forage Seed		Lentils
Forage Silage		Mustard
Grass Hay		Potatoes
Millet		Safflower
Oats		Soybeans
Pasture		Sugar Beets
Popcorn		Sunflowers
Rye		Sweet Potatoes

TABLE 10
RESIDUE REDUCTION

IMPLEMENT	PERCENT RESIDUE REMAINING	
	NONFRAGILE 1/	FRAGILE
<u>PLOWS:</u>		
Moldboard plow	0 - 10	0 - 5
Disk plow	10 - 20	5 - 15
<u>MACHINES WHICH FRACTURE SOIL:</u>		
Paratill/Paraplow	80 - 90	75 - 85
"V" ripper/subsoiler, 12 - 14" deep at 20" spacing	70 - 90	60 - 80
Combination Tools		
Subsoil-chisel	50 - 70	40 - 50
<u>CHISEL PLOWS with:</u>		
Sweeps	70 - 85	50 - 60
Straight chisel spike points	60 - 80	40 - 60
Twisted points or shovels	50 - 70	30 - 40
<u>COMBINATION CHISEL PLOWS:</u>		
Coulter Chisel plows with:		
Sweeps	60 - 80	40 - 50
Straight chisel spike points	50 - 70	30 - 40
Twisted points or shovels	40 - 60	20 - 30
Disk Chisel plows with:		
Sweeps	60 - 70	30 - 50
Straight chisel spike points	50 - 60	30 - 40
Twisted points or shovels	30 - 50	20 - 30
<u>UNDERCUTTERS:</u>		
Stubble-mulch sweep or blade plows with:		
Sweep/"V" Blade > 30" wide	85 - 95	70 - 80
Sweeps 20" - 30" wide	80 - 90	65 - 75
<u>DISK HARROWS:</u>		
Offset		
Heavy plowing > 10" spacing	25 - 50	10 - 25
Primary cutting > 9" spacing	30 - 60	20 - 40
Finishing 7"-9" spacing	40 - 70	25 - 40
Tandem		
Heavy plowing > 10" spacing	25 - 50	10 - 25
Primary cutting > 9" spacing	30 - 60	20 - 40
Finishing 7"-9" spacing	40 - 70	25 - 40

TABLE 10 (Cont.)

RESIDUE REDUCTION

IMPLEMENT	PERCENT RESIDUE REMAINING	
	NONFRAGILE 1/	FRAGILE
<u>DISK HARROWS:</u>		
Tandem		
Light tandem disk after harvest, before other tillage...	70 - 80	40 - 50
One-way disk with:		
12"-16" blades	40 - 50	20 - 40
18"-30" blades	20 - 40	10 - 30
Single gang disk	50 - 70	40 - 60
<u>FIELD CULTIVATORS (including leveling attachments):</u>		
Used as the primary tillage operation		
Sweeps 12"-20"	60 - 80	55 - 75
Sweeps or shovels 6"-12"	35 - 75	50 - 70
Duckfoot points.....	35 - 60	30 - 55
Field cultivators as secondary operation following chisel or disk		
Sweeps 12"-20"	80 - 90	60 - 75
Sweeps or shovels 6"-12"	70 - 80	50 - 60
Duckfoot points.....	60 - 70	35 - 50
<u>FINISHING TOOLS:</u>		
Combination finishing tools with:		
Disks, shanks, and leveling attachments	50 - 70	30 - 50
Spring teeth and rolling basket	70 - 90	50 - 70
Harrows:		
Springtooth (coil tine).....	60 - 80	50 - 70
Spiketooth.....	70 - 90	60 - 80
Flex-tine tooth.....	75 - 90	70 - 80
Roller harrow (cultipacker)	60 - 80	50 - 70
Packer roller.....	90 - 95	90 - 95
Rotary Tiller		
Secondary operation 3" deep	40 - 60	20 - 40
Primary operation 6" deep	15 - 35	5 - 15
<u>RODWEEDERS:</u>		
Plain rotary rod.....	80 - 90	50 - 60
Rotary rod with semi chisels or shovels	70 - 80	60 - 70

TABLE 10 (Cont.)
RESIDUE REDUCTION

IMPLEMENT	PERCENT RESIDUE REMAINING	
	NONFRAGILE 1/	FRAGILE
<u>STRIP TILLAGE MACHINES:</u>		
Rotary tiller, 12" tilled on 40" rows	60 - 75	50 - 60
<u>ROW CULTIVATORS (30" and wider):</u>		
Single sweep per row	75 - 90	55 - 70
Multiple sweeps per row	75 - 85	55 - 65
Finger wheel cultivator	65 - 75	50 - 60
Rolling disk cultivator.....	45 - 55	40 - 50
Ridge till cultivator.....	20 - 40	5 - 25
<u>UNCLASSIFIED MACHINES:</u>		
Anhydrous applicator.....	75 - 85	45 - 70
Anhydrous applicator with closing disks	60 - 75	30 - 50
Subsurface manure applicator	60 - 80	40 - 60
Rotary hoe	85 - 90	80 - 90
Bedders, listers, and hippers	15 - 30	5 - 20
Furrow diker	85 - 95	75 - 85
Mulch treader	70 - 85	60 - 75
<u>DRILLS:</u>		
Hoe opener drills	50 - 80	40 - 60
Semi-deep furrow drill or press drill (7"-12" spacing)..	70 - 90	50 - 80
Deep furrow drill with > 12" spacing	60 - 80	50 - 80
Single disk opener drills.....	85 - 100	75 - 85
Double disk opener drills (conventional)	80 - 100	60 - 80
No-till drills and drills with the following attachments in <u>standing stubble:</u>		
Smooth no-till coulters	85 - 95	70 - 85
Ripple or bubble coulters	80 - 85	65 - 85
Fluted coulters	75 - 80	60 - 80
No-till drills and drills with the following attachments in <u>flat residues:</u>		
Smooth no-till coulters	65 - 85	50 - 70
Ripple or bubble coulters	60 - 75	45 - 65
Fluted coulters	55 - 70	40 - 60

TABLE 10 (Cont.)

RESIDUE REDUCTION

IMPLEMENT	PERCENT RESIDUE REMAINING	
	NONFRAGILE 1/	FRAGILE
<u>DRILLS (Cont.):</u>		
Air seeders: (Refer to appropriate field cultivator or chisel plow depending on the type of ground engaging device used.)		
<u>ROW PLANTERS:</u>		
Conventional planters with:		
Runner openers	85 - 95	80 - 90
Staggered double disk openers	90 - 95	85 - 95
Double disk openers.....	85 - 95	75 - 85
No-till Planters:		
Smooth coulters	85 - 95	75 - 90
Ripple coulters	75 - 90	70 - 85
Fluted coulters	65 - 85	55 - 80
Strip till planters with:		
2 or 3 fluted coulters	60 - 80	50 - 75
Row cleaning devices (8-14" wide bare strip using brushes, spikes furrowing disks, or sweeps).....	60 - 80	50 - 60
Ridge till planter.....	40 - 60	20 - 40
<u>CLIMATIC EFFECTS:</u>		
Over winter weathering 2/ **		
Following summer harvest	70 - 90	65 - 85
Following fall harvest	80 - 95	70 - 80
Over summer weathering	70 - 90	65 - 85

** In northern climates with long periods of snow cover and frozen conditions, weathering may reduce residue levels only slightly, while in warmer climates, weathering losses reduce residue levels significantly. The higher figure will be used in most cases.

1/ If small grain was harvested with a rotary combine, residue is considered fragile.

Converting to Small Grain Equivalent (SGe)

Small Grain Equivalent (SGe) - The wind erosion control equivalent of vegetative cover, compared to a standard condition used for comparative testing in a wind tunnel. The small grain equivalent value of field residues is a function of kind, amount, and orientation of growing plants or plant residues on the soil surface.

Note: Flat small grain in field condition (randomly distributed) must be converted to small grain equivalent.

After the residue reduction actions (Table 10) have been considered and the amount and orientation of air dry remaining crop residue has been determined for the critical wind erosion period, convert to the small grain equivalent. Use the appropriate Chart 1, Pages D-2 to D-29 to make this conversion.

Photo Method for Determining Small Grain Equivalent (SGe)

The residue photos in "Picture Your Residue" or similar photos show several crops with various percent ground cover.

Estimating Small Grain Equivalents (SGe) of Mixed Vegetative Cover consisting of Two or More Components:

Procedure:

1. Describe each major type of vegetative cover and estimate the percentage of total air-dry weight made up of each component.
2. Using the appropriate SGe Chart 1 with the correct curve for each cover type, and using the total air-dry weight of all the vegetative cover on each chart, determine the SGe value of each component type.
3. Multiply the SGe value of each component (from step 2) by that component's percentage of total air-dry weight (from step 1).
4. Add the products (from step 3). The sum of the products is the weighted SGe for the mixed cover.

TABLE 11
PERCENT COVER

POUNDS RESIDUE	SMALL GRAIN	CORN, SORGHUM
200	12%	6%
400	23%	12%
600	32%	18%
800	40%	24%
1,000	48%	29%
1,500	62%	37%
2,000	72%	46%
2,500	80%	54%
3,000	85%	62%
4,000	92%	73%